

Intermec Technologies Corporation 6001 36th Avenue West P.O. Box 4280 Everett, WA 98203-9280

U.S. service and technical support: 1.800.755.5505 U.S. media supplies ordering information: 1.800.227.9947

Canadian service and technical support: 1.800.688.7043 Canadian media supplies ordering information: 1.800.268.6936

Outside U.S. and Canada: Contact your local Intermec service supplier.

The information contained herein is proprietary and is provided solely for the purpose of allowing customers to operate and/or service Intermec manufactured equipment and is not to be released, reproduced, or used for any other purpose without written permission of Intermec.

Information and specifications in this manual are subject to change without notice.

© 2000 by Intermec Technologies Corporation All Rights Reserved

The word Intermec, the Intermec logo, JANUS, IRL, Trakker Antares, Adara, EZBuilder, TE 2000, Data Collection Browser, dcBrowser, Universal Access Point, UAP, Duratherm, EasyCoder, Precision Print, PrintSet, Virtual Wedge, and CrossBar are either trademarks or registered trademarks of Intermec.

AXIS IP Installer and AXIS Print Monitor are a trademarks of AXIS Communications, Lund, Sweden.

Microsoft Windows is a registered trademark of Microsoft Corporation, Redmond, Washington, USA.

Throughout this manual, trademarked names may be used. Rather than put a trademark (TM or [®]) symbol in every occurrence of a trademarked name, we state that we are using the names only in an editorial fashion, and to the benefit of the trademark owner, with no intention of infringement.

Contents

Contents

Before You Begin v

Warranty Information v Safety Summary v Warnings, Cautions, and Notes iv Other Intermec Manuals vi



Downloading and Installing Software

Getting Ready 1-3

Select a Printing Protocol 1-3 Remove Old Intermec Drivers 1-3 Set IPL Printer Label Parameters 1-3

Installing Printer Drivers and Utilities 1-4 Download the InterDriver and ActiveX Controls 1-5 Download the AXIS Print Monitor and IP Installer 1-5 Installation Sequence 1-5 Install the Intermec InterDriver Printer Drivers 1-6 Install the Intermec ActiveX Controls 1-6 Install the AXIS Print Monitor 1-6 Install the AXIS IP Installer 1-7

Assigning an IP Address to the Printer 1-7 Use the AXIS IP Installer 1-7 Use the DOS ARP Command 1-8



Adding a Printer to Windows 95 or Windows 98

Using Windows Printer Wizard 2-3

Configuring the New Printer 2-10



Adding a Printer to Windows NT

Using Windows Print Wizard 3-3

Configuring the New Printer 3-12

Installing EasyCoder Printers in Microsoft Windows Guide



Using ActiveX Controls

Understanding Intermec ActiveX Controls 4-3 Using Intermec ActiveX Controls With Microsoft Word 4-3 Using Intermec ActiveX Controls With Microsoft Excel 4-4 Using Intermec ActiveX Controls With Microsoft Access 4-4



Appendix

Printing Protocols A-3

Deleting Intermec Printer Drivers From Your PC A-4 Windows 95 or Windows 98 A-4 Windows NT A-5

Resetting the AXIS Ethernet Adapter to Factory Default A-6

Adding NetBEUI to Windows 95 and Windows 98 A-7

Adding TCP/IP Printing to Windows NT A-9

Before You Begin

This section introduces you to standard warranty provisions, safety precautions, warnings and cautions, document formatting conventions, and sources of additional product information.

Warranty Information

To receive a copy of the standard warranty provision for this product, contact your local Intermec support services organization. In the U.S. call 1.800.755.5505, and in Canada call 1.800.688.7043. If you live outside the U.S. or Canada, you can find your local Intermec support services organization on the Intermec Web site at www.intermec.com.

Safety Summary

Your safety is extremely important. Read and follow all warnings and cautions in this book before handling and operating Intermec equipment. You can be seriously injured, and equipment and data can be damaged if you do not follow the safety warnings and cautions.

Do not repair or adjust alone Do not repair or adjust energized equipment alone under any circumstances. Someone capable of providing first aid must always be present for your safety.

First aid Always obtain first aid or medical attention immediately after an injury. Never neglect an injury, no matter how slight it seems.

Resuscitation Begin resuscitation immediately if someone is injured and stops breathing. Any delay could result in death. To work on or near high voltage, you should be familiar with approved industrial first aid methods.

Energized equipment Never work on energized equipment unless authorized by a responsible authority. Energized electrical equipment is dangerous. Electrical shock from energized equipment can cause death. If you must perform authorized emergency work on energized equipment, be sure that you comply strictly with approved safety regulations.

Warnings, Cautions, and Notes

The warnings, cautions, dangers, ESD procedures, and notes in this manual use the following format.



Warning

A warning alerts you of an operating procedure, practice, condition, or statement that must be strictly observed to avoid death or serious injury to the persons working on the equipment.

Avertissement

Un avertissement vous avertit d'une procédure de fonctionnement, d'une méthode, d'un état ou d'un rapport qui doit être strictement respecté pour éviter l'occurrence de mort ou de blessures graves aux personnes manupulant l'équipement.



Caution

A caution alerts you to an operating procedure, practice, condition, or statement that must be strictly observed to prevent equipment damage or destruction, or corruption or loss of data.

Conseil

Une précaution vous avertit d'une procédure de fonctionnement, d'une méthode, d'un état ou d'un rapport qui doit être strictement respecté pour empêcher l'endommagement ou la destruction de l'équipement, ou l'altération ou la perte de données.



Note: Notes are statements that either provide extra information about a topic or contain special instructions for handling a particular condition or set of circumstances.

Other Intermec Manuals

You may need additional information when working with the EasyCoder printers in a network or data collection system. Please visit our Web site at www.intermec.com to download many of our current manuals in PDF format. To order printed versions of the Intermec manuals, contact your local Intermec representative or distributor.



Downloading and Installing Software



Use the information in this chapter to become familiar with the installation process and to download and install the necessary printer drivers and utilities to your IPL or Direct Protocol (DP) EasyCoder printer.

Getting Ready

Before you download and install the printer drivers and software utilities, complete the following tasks:

- Select a print protocol.
- Remove old Intermec printer drivers from your PC hard drive.
- Set IPL printer label parameters. (Direct Protocol printer parameters are set later.)

Select a Printing Protocol

Before you use the procedures in this guide, you must select your printing protocol. The two protocols are:

- NetBIOS/NetBEUI
- LPR (TCP/IP)

Unless you are very familiar with your network, you should consult with your network administrator to determine the most appropriate printing protocol. Generally, you will select the NetBIOS/NetBEUI printing protocol if your network does not require IP addresses and you will select the LPR (TCP/IP) printing protocol if IP addresses are required.

For more information, see "Printing Protocols" in the Appendix.

Remove Old Intermec Drivers

Before you download the new InterDriver[™] printer drivers, you must clear any old Intermec printer drivers from your hard drive. For help, see "Deleting Intermec Printer Drivers From Your PC" in the Appendix.



Note: Do not skip this step. If you try to copy over existing InterDriver printer drivers, you may inadvertently cause problems with your Microsoft Windows operating system.

Set IPL Printer Label Parameters

EasyCoder[™] printers that use Intermec Printer Language (IPL) are identified by one of the following model numbers: 3240, 3400, 3440, 3600, 4400, 4420, 4440, 4830, or 7421.

Before you add your IPL printer to Windows, you must use PrintSet[™] to configure the printer label parameters. Because your IPL printer does not have bidirectional

communication with your PC and Windows, these tasks must be done while the printer is connected directly to your PC and not via the network. After sending the label parameters to the printer, you can complete the network connection and add the printer to Windows.

To set IPL printer label parameters

- 1. Connect your EasyCoder printer to your PC using a serial cable.
- 2. Ensure that PrintSet has been loaded on your PC. If not, locate the PrintSet application either at our Web site at www.Intermec.com or on the Printer Companion CD that was shipped with your printer. Follow the PrintSet installation instructions.
- 3. Start PrintSet on your PC.
- 4. From PrintSet's main menu, select Configuration.
- 5. Open each of the configuration options and verify that the default setting is suitable for your IPL printer or make the necessary changes.
- 6. When you have completed the configuration, click on the Send Cfg to Ptr icon or select Send to Printer from the Data Xfer menu option.
- 7. Disconnect the serial cable and complete the physical connection to your Ethernet network.

Installing Printer Drivers and Utilities

Now that you have completed the steps to prepare your PC and EasyCoder printer to receive the new drivers and utilities, you are ready to download and install them.

The following printer drivers and utilities are available on the Internet or on your Printer Companion CD (shipped with your printer).

Utilities	Description
InterDriver TM	Intermec's EasyCoder printer driver that supports a wide range of printer functions.
Intermec®ActiveX® Controls	Intermec's add-on utility that uses Microsoft's ActiveX architecture and permits embedded bar codes or serialized data fields to be inserted into Microsoft Windows [®] applications that support ActiveX Controls. For more information, see Chapter 4.
AXIS Print Monitor for Windows™	Used to configure the EasyCoder printer via Microsoft Windows.
AXIS IP Installer TM	Used to install the new IP address in EasyCoder IPL printers.

1

Download the InterDriver and ActiveX Controls

The drivers and the controls are available either on Intermec's Web site or on your Printer Companion CD.

To find the drivers and controls on Intermec's Web site, go to www. intermec.com and click on Support / Product Support / Downloads / InterDriver. Review the on-screen instructions and complete the steps to download the appropriate versions.

The next table shows the appropriate version of InterDriver for the EasyCoder printer model you are installing.

Printer Model	InterDriver (for IPL Printers)	InterDriver (for DP Printers)	ActiveX Controls
EasyCoder 3240, 3440, 3400, 3600, 4400, 4420,4440, 4830, 7421	х		Х
EasyCoder 201, 301, 401, 501, 501XP, 601, 601XP		Х	Х

Download the AXIS Print Monitor and IP Installer

The AXIS Print Monitor and AXIS IP Installer utilities are available on the Internet or on your Printer Companion CD (shipped with your printer).

To find the utilities on the Internet, go to the AXIS Web site at www.axis.com/glocal/ products/software/ and complete the steps to download the following utilities:

- AXIS Print Monitor for Windows
- AXIS IP Installer

Installation Sequence

You must complete the installation in the following sequence:

- Install InterDriver printer drivers.
- Install the ActiveX Controls.
- Install the AXIS Print Monitor utility.
- Install the AXIS IP Installer utility.

Install the Intermec InterDriver Printer Drivers

- 1. Locate the new InterDriver files on your hard drive or Printer Companion CD. The files have been compressed into a self-extracting zip file for easy downloading. Select Intdripl.exe for IPL printers and select Intdrdp.exe for DP printers.
- 2. Double-click on the self-extracting file for the printer driver. This action will unzip and install the files on your hard drive.
- 3. Select a directory for the controls (the default location is recommended).

Install the Intermec ActiveX Controls

Installing the Intermec ActiveX controls is optional. If you will not be using ActiveX controls with your application, you can skip this step.

1. Uninstall any existing Intermec ActiveX Controls. (From the Windows Start menu, open Programs and select Intermec ActiveX Controls. Click on the uninstall program and follow the screen prompts to complete the uninstall tasks.)

Note: Do not skip the uninstall step. If you try to copy over existing Intermec ActiveX Controls, you may inadvertently cause problems with your Microsoft Windows operating system.

- 2. Locate the new Intermec ActiveX controls file on your hard drive or Printer Companion CD. The files have been compressed into a self-extracting zip file for easy downloading. The filename is accont.exe.
- 3. Double-click on the self-extracting file to unzip and store files on your hard drive.
- 4. Select a directory for the controls (the default location is recommended) and click OK. The setup program will install all components needed for registering and running the Intermec ActiveX controls.

See Chapter 4 for more information about inserting and printing bar code data with ActiveX controls.

Install the AXIS Print Monitor

- 1. Uninstall any existing AXIS Print Monitor files. (From the Windows Start menu, open Programs and select Intermec AXIS Utilities / Print Monitor. Click on the uninstall program and follow the screen prompts to complete the uninstall tasks.)
- 2. Locate the new AXIS Print Monitor file on your hard drive or Printer Companion CD. The files have been compressed into a self-extracting zip file for easy downloading. The filename is setup.exe.
- 3. Double-click on the self-extracting file, and follow the on-screen instructions to unzip and install the utility.

4. Select a directory for the AXIS Print Monitor (the default location is recommended) and click OK.

Install the AXIS IP Installer

The IP Installer is used by EasyCoder IPL printers only.

- 1. Uninstall any existing AXIS IP Installer files. (From the Windows Start menu, open Programs and select Intermec AXIS Communications / IP Installer. Click on the uninstall program and follow the screen prompts to complete the uninstall tasks.)
- 2. Locate the new AXIS IP Installer on your hard drive or Printer Companion CD. The files have been compressed into a self-extracting zip file for easy downloading. The filename is Setup_IPInstaller.exe.
- 3. Double-click on the self-extracting file to unzip and install the utility.
- 4. Follow the installation prompts to install the IP Installer in the default directory (C:\Program Files\AXIS Communications\IP Installer) and create a Program icon group at AXIS Communications\IP Installer.
- 5. When the installation is complete, click Finish.

Assigning an IP Address to the Printer

Select one of the following methods to assign an IP address to the printer:

- Use the AXIS IP Installer (for EasyCoder IPL printers only).
- Use the ARP method to send DOS commands to the printer (for all EasyCoder printers).



Note: The AXIS Ethernet adapter installed in your EasyCoder printer requires a specific IP address and not a dynamically assigned one. If your network dynamically assigns IP addresses to network devices, consult with your network administrator.

Use the AXIS IP Installer

This method can be used to assign an IP address only to an EasyCoder IPL printer.

To assign an IP address using the AXIS IP Installer

- 1. From the Windows Start Menu, select Programs. Select the IP Installer from the AXIS program group.
- 2. For the IP Installer to have access to the Ethernet printer you are installing, you must cycle the power on the EasyCoder printer. The method you will use depends on the type of AXIS Ethernet adapter that is installed in your printer.

- a. If you have an external AXIS Ethernet adapter that is connected to a power supply, disconnect the power supply from the power source (electrical outlet or power strip) and reconnect it.
- b. If you have an internal AXIS Ethernet adapter or an external AXIS Ethernet adapter that receives its power from the printer (requires no power supply), use the printer on/off switch to cycle power.
- 3. The AXIS IP Installer will detect the printer on the network and the serial number of the AXIS Ethernet adapter will be listed in box 1.
- 4. Select the device in box 1, then type the IP address in box 2. Click the Set IP address box.
- 5. When prompted, launch the IP Installer web browser to display the AXIS Ethernet adapter home page.
- 6. Click the configuration tab. Disable DHCP, BOOTP, RARP, and WINS by clicking on the configuration button, and then selecting NO on these items.
- 7. Click Submit to activate the changes.

Note: If this method is not successful, reset the AXIS Ethernet adapter to factory default and repeat the procedure. For help, see the "Resetting the AXIS Ethernet Adapter to Factory Default" procedure in the Appendix.

You are now ready to add your EasyCoder printer to Microsoft Windows. To add a printer to Windows 95 or 98, see Chapter 2, or to add a printer to Windows NT, see Chapter 3.

Use the DOS ARP Command

This method can be used to assign an IP address to either an IPL printer or a DP printer. If you prefer, you can assign an IP address to a DP printer using the keys on the printer's front panel. See your printer user's manual for instructions.

To assign an IP address using the DOS ARP Command

- 1. Start a DOS window.
- 2. At the DOS prompt, type the following commands:

```
arp -s nnn.nnn.n.nnn nn-nn-nn-nnping nnn.nnn.n.nnnarp -d nnn.nnn.n.nnWhere:nnn.nnn.n.nnis the IP address for the Ethernet adapter.nnn-nn-nn-nn-nnis the Ethernet address (or MAC) for the<br/>Ethernet adapter; located on the adapter<br/>on the back of the printer.
```

Example:

```
arp -s 192.168.3.191 00-40-8c-10-00-86
ping 192.168.3.191
arp -d 192.168.3.191
```

3. Exit DOS and return to Windows.

You are now ready to add your EasyCoder printer to Microsoft Windows. To add a printer to Windows 95 or 98, see Chapter 2, or to add a printer to Windows NT, see Chapter 3.



Adding a Printer to Windows 95 or Windows 98



The information in this chapter guides you through the process of adding a network printer to Windows 95 or Windows 98. See Chapter 3 for information about adding a printer to Windows NT.

Using Windows Printer Wizard

ß

Note: If you selected the NetBIOS/NetBEUI printing protocol, you must complete the "Adding NetBEUI to Windows 95 and Windows 98" procedure in the Appendix before proceeding with this chapter.

1. From the Windows Start Menu, open the Printers menu.



2. Double-click the Add Printer Icon.



3. Click Next.



4. Click Local Printer, then click Next.





5. Click Have Disk to add the Intermec printer driver, InterDriver.

Note: If Intermec Printer Language (IPL) or Direct Protocol (DP) commands are to be used from a text file, select Generic, Generic / Text Printer. See your printer programming language reference manual for information about using a text editor, such as Notepad, to print labels.

Add Prin	ter Wizard				
Ì	Click the manufa installation disk, o documentation fo	cturer and click Have rr a compa	model of your pr Disk. If your prin tible printer.	inter. If your prin hter is not listed,	ter came with an consult your printer
Manufar Apple AST AT&T Brother Bull C-Itoh Canon	sturers:	Prin Ap Ap Ap Ap	iters: ple LaserWriter ple LaserWriter ple LaserWriter ple LaserWriter ple LaserWriter I nle LaserWriter I	I NT Personal NT I NTX If Ig Plus	▲ ■ Have Disk
			< <u>B</u> ack	Next>	Cancel

6. Click Browse.

۴Ŷ

Install Fr	om Disk	×
_	Insert the manufacturer's installation disk into the drive selected, and then click OK.	OK Cancel
	Copy manufacturer's files from: A:\	Browse

7. Locate the directory for the appropriate version of InterDriver, then click OK. For information about which driver to select for your printer, see Chapter 1.





8. Select the printer model, then click Next.

Click the manufacturer and model of your printer. If your printer came with installation disk, click Have Disk. If your printer is not listed, consult your documentation for a compatible printer. Printers: EasyCoder 501 (203 dpi) EasyCoder 501 (203 dpi) EasyCoder 501 (203 dpi) EasyCoder 501 (203 dpi) EasyCoder 501 XP (605 dpi) EasyCoder 601 XP (305 dpi) EasyCoder 601 XP (305 dpi)	
Printers: EasyCoder 401 (203 dpi) EasyCoder 501 (203 dpi) EasyCoder 501 (300 dpi) EasyCoder 601 XP (305 dpi) EasyCoder 601 XP (305 dpi) EasyCoder 601 XP (305 dpi) Have Disk	an printer
EasyCoder 401 (203 dpi) EasyCoder 501 (203 dpi) EasyCoder 501 (300 dpi) EasyCoder 501 XP (305 dpi) EasyCoder 601 (203 dpi) EasyCoder 601 XP (305 dpi) Have Disk	
EasyCoder 501 (300 dpi) EasyCoder 501 XP (305 dpi) EasyCoder 601 (203 dpi) EasyCoder 601 XP (305 dpi) <u>H</u> ave Disk	-
EasyCoder 601 (203 dpi) EasyCoder 601 XP (305 dpi) <u>H</u> ave Disk	
<u>Have Disk</u>	
<u>H</u> ave Disk	⊡
< <u>B</u> ack Next> Cano	a

For IPL Printers

For Direct

Protocol Printers

Add Prin	ter ₩izard			
Ì	Click the manufacturer a installation disk, click Ha documentation for a con	and model of your pri ave Disk. If your prin npatible printer.	nter. If your print ter is not listed, (er came with an consult your printer
Printers:				
EasyCo	oder 3600			-
EasyCo	ader 4400C (152 api) ader 4400C (203 dpi)			
EasyCo	oder 4420			
EasyCo	oder 4830			
l EasuCo	nder 7421			
				<u>H</u> ave Disk
		< <u>B</u> ack	Next >	Cancel

9. Select Replace existing driver, then click Next. This screen will not be seen during the first installation of the InterDriver.

For Direct Protocol Printers







10. Select the appropriate port for your printing protocol, then click Next.

For NetBIOS/ NetBEUI printing protocol

Select a port that follows the format AXnnnnn.LP1 or ITCnnnnn.FIF where nnnnn matches the AXIS Ethernet adapter serial number.

(For example: AX3548DE.LP1 or ITC341C23.FIF)

Add Printer ₩izard Click the port you want to use with this printer, and then click Next. Available ports: COM1: Communications Port -COM2: Communications Port FILE: Creates a file on disk ITC00361D.FIF AXIS Port ECP Printer Port LPT1: VINTERMEC_CORPORATION_ENTER LPT2: LPT3: pr1@10.20.15.81 AXIS Port • Configure Port. < <u>B</u>ack Next> Cancel

For LPR (TCP/ IP) printing protocol

Select LPT1 (this is a temporary setting).

11. Verify that the name of your printer appears in the Printer name box, then click Finish.



Configuring the New Printer

Now that you have added your new EasyCoder printer to Windows, you are ready to configure the printer.

1. Place the cursor over the new printer icon and click the right mouse button. Select Properties.



2. From the Properties window, select the Details tab.

EasyCoder 501 XP (305 dpi) Properties	? ×
Fonts BarFonts Stock Options Testing General Details Regional Settings Page Setup (About àraphics
EasyCoder 501 XP (305 dpi)	
<u>C</u> omment:	
Separator page: [none]	
Print <u>I</u> est Page	1
	· · · ·
UK Cancel Apply	Help

F¥

Note: Skip steps 3 through 6 if you selected NetBIOS/NetBEUI printing protocol.

3. Click Add Port. LPR (TCP/IP) users only.

EasyCoder 501 XF	(305 dp)		
int to the following part			
PT1_ELPPorter For		•	Add Port
tind a solice the full solice data			Daleta Pod.
LaspCoder 501 >0° (305 d)	ni.	-	Neg Driver_
Capture Printer Port		Egd	Capture
Tineout settings Not pelected	5 second	4- ¹	
Transmission petry	5 second	6	

4. Select Other, then select AXIS Port, and click OK. LPR (TCP/IP) users only.



5. Select the LRP (TCP/IP) printing protocol, and click OK. LPR (TCP/IP) users only.

Add AXIS Port	×
	OK
Print using the following protocol:	Cancel
LPR (TCP/IP) NetBIOS/NetBEUI	Help
RAW (TCP/IP)	

6. Enter the printer IP address and enter pr1 for the logical printer name. Click OK. (If DHCP is enabled, enter the Printer Host name rather than the IP address.) LPR TCP/IP users only.

Add AXIS LPR Port	×
Host name or IP address of the print server	ОК
10.20.15.81	Cancel
Logical printer name	Help
pr1	

- EasyCode: 4420 Properties 7 X Bar Fonts | Options | Printer Settings | Storage Memory | About General Ontain | Regional Settings | Page Setup | Graphics | Fonts EasyCoder 4420 Pint to the following got 49(393020 LP1 14905 Port Add Poet • Delete Port. Part yang the following driver Neg Dave. EasyCoder 4420 • Capture Parter Port. EpdCaphae. Tyneout setting: Not palected seconds Transmission getty: secondi Spool Settings. Port Settings ŪK. Cancel Apple
- 7. From the Print to the following port: list box, select the port. Your selection depends on the printing protocol you will use.



For NetBIOS/

NetBEUI

Foreir Barranes 5000. Serenal Defails Regional S EasyCoder 501 XP (305 (Co	Upsoni tenting Adau Settings Page Setup Graphic opy 2]
The following part	
10010-20-2017 (4445 Fed	Add Part.
	Delete Part.
E acyCoder 501 XP (305 dpi)	New Drivet.
Capture Printer Plat	Epd Capture
Tyneout settings Not pelected	seconds
Transmission jetzy.	seconds
Spool Sett	tings

8. Select the Page Setup tab. Set the Label Stock by picking from the predefined list or selecting a custom setting by clicking New.

Fonts General Label Stoc <u>N</u> ame:	BarFonts Stock Details Regional S k UserDefined (4.00 in x 2	Options Testing Abo ettings Page Setup Graphi 2.00 in)	
	Ne <u>w</u>	Edit	
	Import Stock List	Export Stock List	
Preview	Orientation C Portrait C Landscape C Portrait 180 C Landscape	* 180*	
- Miscellane <u>C</u> opies:	ous	Advanced Options	
© 1999 Intermec Technologies Corporation.			
	© 1997-1999 Sea Authors of the BarTe	agull Scientific, Inc., ender® label software.	
Г	0K Cam	cel Applu Help	

For IPL Printers

For Direct

Protocol Printers

EasyCoder 4420 Properties				
BarFontz Options Printer Settings Storage Memory About Beneral Details Regional Settings Page Setup Busphics Fonts				
Label Stock Nome: User Defined (4.00 in x 4.00 in)				
NegEdtDelete				
Import Stock Lint Export Stock Lint.				
Preview Orientation Effects				
Miscellaneous Copies: 1				
@ 1999 Internec Technologies Corporation.				
© 1997-1999 Seegul Scientific, Inc., Authors of the BarTender® label software.				
OK Cancel Supp Help				

9. If you are installing an IPL printer, skip this step. Select the Stock tab. In Setup Options, select Use Current EasySet System / Printer Settings.

General Details neglorial settings Page Setup Graphics Fonts Bar Fonts Stock Options Testing About Setup Options Image Setup Use Current EasySet System / Printer Settings Image Setup Media Settings Media Settings Image Setup Image Setup Constrast: 0% Image Setup Method: Thermal Transfer Image Setup Constrast: 0% Image Setup Stock: GP02 - Matte Coated Image Setup Image Setup Image Setup Ribbon Constant: 80 Label Offset: Image Setup	Sycoder 5	UT XP (305 dpi) Properties 24
Setup Options Image: Send Changes Only Media Settings Method: Thermal Transfer Type: Label (with Gaps) Stock: GP02 - Matte Coated Ribbon Constant: 80 Label Offset: Ribbon Eactor: 25	Fonts	BarFonts Stock Options Testing About
Ise Current EasySet System / Printer Settings Image: Settings Media Settings Method: Thermal Transfer Type: Label (with Gaps) Stock: GP02 - Matte Coated Ribbon Constant: 80 Label Offset: Ribbon Eactor: 25	r ⊢Setun Oni	tions
Media Settings Method: Thermal Transfer Iype: Label (with Gaps) Stock: GP02 - Matte Coated Ribbon Constant: 80 Label Offset: Ribbon Eactor: 25	I Use C	Surrent EasySet System / Printer Settings
Media Settings Method: Thermal Transfer Contrast: 0% Type: Label (with Gaps) Stock: GP02 - Matte Coated Ribbon Constant: 80 Label Offset: 0 Ribbon Eactor: 25	🔽 Send	Changes Only
Method: Thermal Transfer Contrast: 0% Lype: Label (with Gaps) > Stock: GP02 - Matte Coated > Ribbon Constant: 80 Label Offset: 0 Ribbon Eactor: 25	– Medie Sei	ttings
Lype: Label (with Gaps) Stock: GP02 - Matte Coated Ribbon Constant: 80 Label Offset: 0 Ribbon Eactor: 25	Method:	Thermal Transfer
Stock: GP02 - Matte Coated Ribbon Constant: 80 Label Offset: 0 Ribbon Eactor: 25	 Type:	Label (with Gaps)
Ribbon Constant: 80 Label Offset: 0 Ribbon Eactor: 25	<u>S</u> tock:	GP02 - Matte Coated 👻
Ribbon <u>Eactor:</u> 25	Ribbon <u>C</u> i	onstant: 80 Label Offset: 0
	Bibbon Fr	ector: 25
		20(0).
	r	
		UK Cancel <u>A</u> pply Help

10. Select the Testing tab for the DP printers or select the Printer Settings tab for the IPL printers. Click the Print Test Label button and verify that a test label was printed.

gend hie to Paritet.	Logging Options	
lantenance		
Earn Feed	Detaut	
Clean Feed	1000 m	
Text Feed	Bebook	
Qitan Feed		



This completes the tasks to add a printer to Microsoft Windows 95 or Windows 98. See Chapter 4 for information about using Intermec ActiveX Controls to add bar codes to Windows Office applications.

For Direct Protocol Printers



Adding a Printer to Windows NT



The following procedure guides you through the process of adding a network printer to Windows NT.

Using Windows Print Wizard

f¥

Note: If you selected the TCP/IP print protocol, you must complete the "Adding TCP/IP Printing to Windows NT" procedure in the Appendix before proceeding with this chapter.

1. From the Windows Start Menu, open the Printers menu.



2. Double-click the Add Printer icon.



3. Select My Computer, then click Next.

Add Printer Wizard	X
E	This wizard helps you install your printer or make printer connections. This printer will be managed by:
	All settings will be managed and configured on this computer. Network printer server Connect to a printer on another machine. All settings for this printer are managed by a print server that has been set up by an administrator.
	< <u>B</u> ack <u>N</u> ext > Cancel

4. In the Add Printer Wizard window, Click Add Port.

Add Printer Wizard				×
	Click the check by Documents will pri	ox next to the port int to the first avail	(s) you want to use able checked port	
	Port	Description	Printer	
	10.20.13.9		Generic / Te	
	10.20.13.2		EasyCoder 4	
	LPT1:	Local Port	EasyCoder 7	
	LPT2:	Local Port		
	LPT3:	Local Port		
	🗆 сом1:	Local Port		•
	Add Port	pooling	<u>C</u> onfigure Port	
		poomig		
	< <u>B</u> a	ck <u>N</u> ext>	Cancel	

1	Printer Ports ? 🗙
	Available Printer Ports:
	AXIS Port Digital Network Port Lexmark DLC Network Port Lexmark TCP/IP Network Port Local Port LPR Port
	<u>N</u> ew Monitor
	New <u>P</u> ort Cancel

For NetBIOS/ NetBEUI

For LPR
(TCP/IP)

Printer Ports	×
Available Printer Ports:	
Digital Network Port Lexmark DLC Network Port Lexmark TCP/IP Network Port Local Port LPR Port	
<u>N</u> ew Monitor	
New Port	

5. Select the appropriate port for the printing protocol being used, then click New Port.

6. Select the printing protocol, then click OK. If you are an LPR (TCP/IP) user, skip this step.

Add AXIS Port	×
[OK
Print using the following protocol:	Cancel
LPR (TCP/IP) NetBIOS/NetBEUI RAW (TCP/IP)	Help

7. Select or the appropriate port for you printing protocol, then click OK.

Add AXIS NetBIOS/NetBEUI Port	×
Available AXIS NetBIOS/NetBEUI Ports: AX354666.LP1 AX354BDE.LP1 AX35206D.LP1 ITC003603.FIF ITC00361B.FIF	OK Cancel Help

For NetBIOS/ NetBEUI printing protocol

Select a port that follows the format AXnnnnn.LP1 or ITCnnnnn.FIF where nnnnn matches the AXIS Ethernet adapter serial number. (For example: AX354666.LP1 or ITC003603.FIF)

For LPR (TCP/IP) printing protocol

Name of printer or print queue on server must be set to PR1. (This is a temporary setting.)

Add LPR compatible printer		X
Name or address of server providing lpd:	10.20.13.204	ОК
Name of printer or print queue on that server:	pr1	Cancel
		<u>H</u> elp

3



8. Ensure that the port being used has a check in the box, then click Next.

For LPR (TCP/IP)

For NetBIOS/

NetBEUI



9. Click Have Disk.

Add Printer Wizard Click the manufactu installation disk, clici printer documentatio	rer and model of your printer. If your printer came with an k Have Disk. If your printer is not listed, consult your on for a compatible printer.
Manufacturers: Agfa Apple APS-PS AST AT&T Brother Bull	Printers: AGFA-AccuSet v52.3 AGFA-AccuSetSF v52.3 AGFA-AccuSet 8005F v52.3 AGFA-AccuSet 8005F v2013.108 AGFA-AccuSet 1000 AGFA-AccuSet 10005F v52.3 Have Disk
	< <u>B</u> ack <u>N</u> ext > Cancel

10. Locate the directory for the appropriate version of InterDriver, then click OK. For information about selecting the right driver, see Chapter 1.



For IPL Printers



For Direct Protocol Printers

- Add Printer Wizard х **Protocol Printers** Click the manufacturer and model of your printer. If your printer came with an installation disk, click Have Disk. If your printer is not listed, consult your printer documentation for a compatible printer. C Stra Printers: EasyCoder 401 (203 dpi) ٠ EasyCoder 501 (203 dpi) EasyCoder 501 (203 dpi) EasyCoder 501 (300 dpi) EasyCoder 501 XP (305 dpi) EasyCoder 601 (203 dpi) EasyCoder 601 XP (305 dpi) • Have Disk.. < <u>B</u>ack Cancel $\underline{N}ext >$
- 11. Select the printer model, then click Next.

For IPL Printers

For Direct

Add Prin	nter Wizard 🛛 🗙
٩	Click the manufacturer and model of your printer. If your printer came with an installation disk, click Have Disk. If your printer is not listed, consult your printer documentation for a compatible printer.
Printers: EasyC EasyC EasyC EasyC EasyC FasyC	: oder 3600 oder 4400C (152 dpi) oder 4420 oder 4420 oder 4440 oder 4830 mder 7421
	< <u>B</u> ack <u>N</u> ext > Cancel

12. Select Replace existing driver, then click Next.



13. Verify that your newly installed printer appears in the Printer name window. Then click Next.



14. Select Not shared, and click Next.

Add Printer Wizard		×
	Indicate whether this printer will be shared with other network users. If you choose sharing give this printer a share name.	
	C Shared Not shared	
	Share Name:	
	Select the operating systems of all computers that will be printing to this printer.	
	Windows 95 Windows NT 4.0 MIPS Windows NT 4.0 Alpha	
	Windows NT 4.0 PPC	
	Windows NT 3.5 or 3.51 MIPS	
		_
	< <u>B</u> ack <u>N</u> ext > Cancel	

15. Select No, then click Finish.

Add Printer Wizard	×
	After your printer is installed, you can print a test page so you can confirm that the printer is set up properly. Would you like to print a test page? Yes (recommended) No
	< <u>B</u> ack Finish Cancel

Configuring the New Printer

1. From the Windows Start Menu, select Settings and Printers. Move the cursor over the newly installed printer icon in the Printers window, and click the right mouse button. Select Document Defaults.





2. Select the Page Setup tab, and set the Label Stock. Pick from the predefined list or select a custom setting by clicking New.

💣 E asyCoder	501 XP (305 dpi) D	efault		? ×
Page Setup	Graphics Stock Op	tions About		
⊢ Label Stoci	k			
Name:	USER (4.00 in x 2.00 in			-
	Ne <u>w</u>	<u>E</u> dit	<u>D</u> elete	
	Import Stock List	Ex	port Stock List	
ABC	Orientation © Portrait © Landscape © Landscape	• 180°	fects Mirror Image Negatýve	
- Miscellane <u>C</u> opies:	bus	<u>A</u> dvanc	ed Options	
	© 1999 Intermec Teo	chnologies Corp	ioration.	
	© 1997-1999 Sea Authors of the BarTe	agull Scientific, I ender® label sol	nc., ftware.	
	01	Ca	ancel H	elp

For Direct Protocol Printers

For	IPL	Prin	ters

🍯 E asyCode	er 3240 Default 🥂 🤗	X
Page Setup	Graphics Options About	
Label Sto	ock	
<u>N</u> ame:	USER (3.00 in x 4.00 in)	
	New Edit Delete	
	Import Stock List Export Stock List	
Preview AB(Orientation Effects	
Miscellan <u>C</u> opies:	eous 1 Advanced Options	
	© 1999 Intermec Technologies Corporation. © 1997-1999 Seagull Scientific, Inc., Authors of the BarTender® label software.	
-	OK Cancel Help	

3. For DP printers, select the Stock tab and check the Use Current EasySet System/Printer Settings box. Click OK. Skip this step if you are adding an IPL printer.

	ings	
[ethod:	Thermal Transfer Contrast: ()% 🔻
ype:	Label (with Gaps)	
tock:	GP02 - Matte Coated 📃 💌	
ibbon <u>C</u> a	nstant: 80 Label Offset: 0	
ibbon <u>F</u> a	ctor: 25	

4. Move the cursor over the newly installed printer and click the right mouse button. Select Properties.





For Direct	af Landoder Still VP (105 del Presentiar 17 17	
Protocol Printers	General Ports Scheduling Sharing Security Readonal Software Fonts Bar Fonts Texting Adout	
	Testing	
	Send File to Printes. Logging Options.	
	Maintenance	
	Earn Feed	
	Share Freed 0.00 m	
	Text.seo Becox	
	OK Cancel Help	
	A Card and 22th December 20th	
For IPL Printers	General Posts Scheduling Sharing Security Regional Settings	
	Fonts BarFonts Printer Settings Storage Memory About	
	Configure	
	Use the Configure button to view and/or change various printer settings such as the print speed, deformers, stock type, or sensitivity. When possible, the current estings will star be uplaceded from the	
	privites.	
	Testing Print Test Label Type: Generic Test	
	Send File to Printer. Logging Options	
	Maintenance	
	Phinter Beset Brook Jackson	
	Eactory Defaults Readable Control Characters	
	OK Cancel Heb	
T	his completes the tasks to add a printer to Microsoft Windows NT formation about using Intermed Active X Controls to add bar code	. See Chapter 4 for
aj	plications.	
	-	

5. Click the Printer Settings tab for IPL printers or the Testing tab for Direct Protocol Printers. Click the Print Test Label button and verify that a Test Label printed.



Using ActiveX Controls



With Intermec ActiveX controls you can use Microsoft Word, Microsoft Excel, or Microsoft Access to print bar code labels using your newly installed EasyCoder Ethernet printer.

Understanding Intermec ActiveX Controls

Intermec ActiveX Controls are ready-to-run components that you can use to print bar codes from Windows Microsoft Office or other popular Windows applications. Using Intermec Active X Controls to print bar codes provides the following advantages:

- Uses resident printer bar code symbologies.
- Provides configurable properties, such as symbology, text, font, and orientation.
- Eliminates the need for additional applications, bar code fonts, or add-on tools.
- Inserts scannable bar codes into documents by sending EasyCoder command language sequences to the printer, not bit-mapped graphical data.
- Enables the printer to deliver high throughput while maintaining excellent print quality.
- Uses fixed data, serialized data, data from a database, or data through a programming interface.

To learn more about ActiveX controls, see your application user's manual.

Using Intermec ActiveX Controls With Microsoft Word

- 1. Start Microsoft Word[®].
- 2. From the File Menu, select Print. In the Printer name list box, select the EasyCoder printer. Click OK.
- 3. From the Insert menu, select the Object command.
- 4. Select Intermec ActiveX Bar Code from the Object type list box. Click OK. The Intermec ActiveX Bar Code is inserted into your Word document.
- 5. Change the bar code properties.
 - a. Double click on the bar code. The Properties screen appears. Edit the properties of the bar code.
 - b. When finished, click OK. The changes take effect immediately.
- 6. Print the label.

Using Intermec ActiveX Controls With Microsoft Excel

- 1. Start Microsoft Excel[®].
- 2. From the File Menu, select Print. In the Printer name list box, select the EasyCoder printer. Click OK
- 3. From the View menu, select Toolbars / Control Toolbox from the drop-down menu.
- 4. Select the Design Mode button on the Control toolbar.
- 5. From the Insert menu, select the Object command. Select Intermec ActiveX Bar Code from the Object type list box. Click OK.
- 6. Change the bar code properties.
 - a. Place the cursor over the bar code and click the right mouse button.
 - b. From the ActiveX menu that appears, select Intermec ActiveX Bar Code / Properties.
 - c. The Properties screen appears. Edit the properties of the bar code.
 - d. When finished, click OK. The changes take affect immediately.
- 7. Bind the data.
 - a. Place the cursor over the bar code and click the left mouse button.
 - b. In the Control Toolbox, click the Properties icon.
 - c. Add a spreadsheet cell to the LinkedCell field. Close the control. The Intermec ActiveX Bar Code control changes to reflect the value entered into the spreadsheet cell.
- 8. Print the label.

Using Intermec ActiveX Controls With Microsoft Access

- 1. Start Microsoft Access[®].
- 2. From the File Menu, select Print. In the Printer name list box, select the EasyCoder printer. Click OK
- 3. In Design view, open the Report you will modify.
- 4. From the Insert menu, select the Custom Control command.
- 5. Select Intermec ActiveX Bar Code from the Object type list box and click OK. The Intermec ActiveX Bar Code bar code is inserted into your Access document.
- 6. Change bar code properties by double-clicking on the bar code. When the Properties screen appears, edit the properties. When editing is complete, click OK. The changes take effect immediately.



- 7. Bind the data.
 - a. From the Edit menu, select Report.
 - b. From the View menu, select Properties and select the Data tab.
 - c. Select Table or Query for the source data from the Record Source field.
 - d. Close the Properties window.
 - e. Place the cursor over the bar code and click the right mouse button. Select Properties.
 - f. From the Control source field, select the entry to bind to the bar code.
 - g. Close the Properties window.
- 8. Print the label.



Use the information in this appendix to complete special installation tasks.

Printing Protocols

Before adding a printer to Windows, you must select the appropriate printing protocol. The following table provides additional information that may help you understand the two printing protocols available with your EasyCoder Ethernet printer. If you are unsure which protocol to select, review this information with your network administrator.

Protocol	Protocol Description
NetBIOS/NetBEUI	• Peer-to-peer printing.
	• Restricted to the same subnet or networks without subnets. NetBIOS/NetBEUI is not a routable protocol.
	• No IP Address is necessary.
	• With AXIS Print Monitor installed, EasyCoder printer ports will be automatically listed in the ports list.
	• Format for NetBIOS/NetBEUI port is <name>.LP1 where <name> is AX followed by last six digits of the AXIS Ethernet adapter serial number (for example, AX560B35.LP1).</name></name>
	• The network administrator may change the port name later, if required.
LPR (TCP/IP)	• Peer-to-peer printing.
	• Not restricted to the same subnet. Possible to print across the Internet.
	• IP Address is required for the printer.
	• Ports must be added manually.
	LINIX I DD stale asigting I asigs a minter some some of asigter as

• UNIX LPR style printing. Logical printer name, name of printer, or print queue must be set to PR1.

If an IP address is required by your PC, you can assume that the printer also needs an IP address. You can check your PC for an IP address by accessing Windows Control Panel and clicking on the Network icon. Check the list for an installed TCP/IP component. If you find one, assume that your network requires an IP address and contact your network administrator to request a new IP address for your EasyCoder printer. For information about assigning an IP address to the printer, see the procedures in Chapter 1.

If you do not find an TCP/IP component, you still may require an IP address if you will be printing to the EasyCoder printer across a subnet.

If you selected TCP/IP because you will be printing across subnets, you must determine if subnet routers let BOOTP and DHCP packets pass through. If they do, you can simply request an IP address for your printer and complete the installation. However, if

subnet routers are NOT configured to let BOOTP and DHCP packets pass through, you will need to complete the printer installation in one of the following ways:

- Request an IP address for the printer that is within its final location subnet. Then, complete the installation of the printer at a Windows PC that is running in the same subnet as the printer. For instructions, see Chapter 1.
- Request two IP addresses, one for your PC subnet (the setup address) and one for the final subnet of the printer (the final address). At your PC, assign the setup IP address to the printer and complete the installation. Just before the printer is sent to its final location, assign the final IP address to the printer. For information about assigning IP addresses, see Chapter 1.

Deleting Intermec Printer Drivers From Your PC

Windows 95 or Windows 98

- 1. From the Start menu, Select Settings / Printers.
- 2. In the Printers window, delete Seagull and Intermec printer icons and set the default printer to a well-known printer, such as an HP LaserJet.
- 3. (Optional step.) In Windows Explorer, delete the directory intermec/intrdrvr and all its subfolders.
- 4. In Windows Explorer, select Windows/System directory. From the Tools tab, select Find Files or Folders. Find and delete files matching the following:

sss*.* ipl*.* oss*.* epl*.* oin*.* ubi*.*

- 5. From the Tools Menu, select Find Files or Folders. Search and delete all files with the extension *.inf that also contain Seagull in the text. Use the Advanced tab to enter text.
- 6. Reboot your PC.

Your hard drive is now clear of old Intermec printer drivers and you are ready to install the new printer drivers.



Windows NT



Caution The following procedure directs you to open and edit the Registry. Use caution and follow the procedure exactly. Failure to comply may disable your PC.

- 1. From Windows Start Menu, select Settings and Printers. Delete all seagull and Intermec drivers by deleting the printer icons in the Printers window. Set your default printer to a well-known general printer such as an HP LaserJet.
- 2. From the Control Panel, select Services. Highlight the Spooler and click Stop.
- 3. Using Windows Explorer, access the winnt/system32 directory. From the Tools menu, select Find/Files or Folders. Locate and delete the following files:

sss*.* ipl*.* oss*.*

epl*.* oin*.* ubi*.*

- 4. Using Windows Explorer, select Find from the Tools menu. Select Files or Folders. In the c:\winnt directory search for and delete all files containing the extension *.inf and containing the text seagull. (Use the features on the Advanced tab to enter text.) Close Explorer.
- 5. From the Start menu, select Programs and Command Prompt.
- 6. At the C: prompt, type regedit and press Enter. The Registry Editor window appears.
- 7. Open the HKEY_CURRENT_USER folder, the Printers folder and the Settings folder. Delete any values for EasyCoder or Intermec printers.
- 8. Open the HKEY_LOCAL_MACHINE folder and the SYSTEM folder. For each subfolder in the SYSTEM directory, search for and delete any keys that correspond to EasyCoder or Intermec printers.
- 9. Open the HKEY_USERS folder. Open each subfolder and search for and delete all values for EasyCoder or Intermec printers.
- 10. Close the Registry Editor window. Type Exit at the C: prompt to return to Windows.
- 11. Reboot your PC.

Your hard drive is now clear of old Intermec printer drivers and you are ready to install the new printer drivers.

Resetting the AXIS Ethernet Adapter to Factory Default

- 1. Remove the Ethernet cable from the AXIS Ethernet adapter.
- 2. Turn off the Ethernet adapter.
 - If the Ethernet adapter uses a power supply, disconnect the power supply from the electrical source.
 - If no power supply is required by the Ethernet adapter, turn off the printer.
- 3. Press and hold the AXIS adapter test button. While pressing the test button, turn on the AXIS adapter by turning on the printer or reconnecting the power supply cord. Keep the test button pressed for at least 5 seconds after restoring power or until the Network LED flashes 5 times at 1 second intervals.
- 4. Release the test button and wait for 5 LED flashes.
- 5. Press and hold the test button again until the Network LED remains constantly lit.
- 6. Turn off the AXIS adapter.
- 7. Reinstall the Ethernet cable to the AXIS adapter.
- 8. Restart the AXIS adapter by turning it on. The AXIS adapter is now reset to factory default settings.



Adding NetBEUI to Windows 95 and Windows 98



1. From Windows Start button, open the Control Panel.

2. Double-click the Network icon.



3. Click Add.



4. Select Protocol, then click Add.



5. Select Microsoft and NetBEUI. Then click OK.



A

Adding TCP/IP Printing to Windows NT

1. From the Windows Start Menu, open the Control Panel.

-		
👼 <u>P</u> rogram	s 🔸	
<u> D</u> ocume	ents 🕨 🕨	
🕵 <u>S</u> ettings	۲.	🔯 Control Panel
🔊 <u>F</u> ind	۲.	Printers
🥏 <u>H</u> elp		🖺 <u>T</u> askbar
🚰 <u>R</u> un	-	
🗊 Shut Do	wn	
Start 🖁	🔄 Inbox - Microsoft Ou.	💋 140. Traffic - The L

2. Double-click the Network icon.



Network ?	×
Identification Services Protocols Adapters Bindings	_
Network Services:	
Computer Browser Microsoft TCP/IP Printing NetBIOS Interface Novell Client for Windows NT Novell Workstation Manager RPC Configuration Server Simple TCP/IP Services	
Add <u>R</u> emove <u>P</u> roperties <u>U</u> pdate	
Description: Enables Windows NT to print to TCP/IP-connected printers or to printers that are physically attached to UNIX computers. Network Access Order	
OK Cancel	

3. Select the Services tab and click on Microsoft TCP/IP Printing. then click Add.

4. Select Microsoft TCP/IP Printing. Click OK.

